DepthVista

DepthVista CMD Build Manual







Disclaimer

e-con Systems reserves the right to edit/modify this document without any prior intimation of whatsoever.



Contents

INTRODUCTION TO DEPTHVISTA	3
Prerequisites	3
DESCRIPTION	3
INSTALLING OPENCV 4.2.0	5
BUILDING DEPTHVISTA APPLICATION	6
RUNNING DEPTHVISTA APPLICATION	12
SUPPORT	13
FAQ	14



Introduction to DepthVista

This document describes how to build the DepthVista console application step by step on the host PC (Windows).

Prerequisites

The prerequisites are as follows:

- DepthVista console application source code.
- Visual Studio (VS 2017).
- DepthVistaSDK.

Description

DepthVista has USB interface controller with USB Type-C connector to interface with the host PC. It is a ready-to-manufacture camera board with all the necessary firmware built-in and is compatible with the UVC version 1.0 standard. You can integrate this camera into the products, and this helps to cut short the time-to-market.

DepthVista is a UVC compatible and will work with the standard drivers available with Windows and Linux OS. There is no need for any additional driver installation. So, video streaming through UVC is possible without any special drivers on OSes that have built-in support for UVC standards.

Table 1: DepthVista supported Format, Resolutions, and Frame Rates

S.No	Format	Camera Mode	Resolution	Frame Rate (fps)
				USB 3.2 Gen 1
1	UYVY	RGB Mode	2.3MP (1920 x 1200)	30
			FHD (1920 x 1080)	30
			HD (1280 x 720)	60
			VGA (640 x 480)	60
2	Y16	TOF Mode	Depth (640 x 480)	30
	(RAW 12-bit)		IR (640 x 480)	30
			Depth + IR (640 x 960)	30



3	RGB-D Mode	_	1280 x 600 (RGB-D)	30
		Mode	1443 X 960 (RGB-D)	30

TOF camera in DepthVista can be used in two depth modes as follows:

- Far Mode: Effective depth range is between 1000 mm to 6500 mm.
- Near Mode: Effective depth range is between 200 mm to 1200 mm.

The TOF camera controls of DepthVista are as follows:

- TOF Data Mode
- TOF Depth Range
- TOF Mask
- TOF Gain

The RGB camera controls of DepthVista are as follows:

- Brightness
- Contrast
- Saturation
- Gamma
- Gain
- Sharpness
- White Balance
- Exposure
- Power line frequency



Installing OpenCV 4.2.0

DepthVista Console application requires OpenCV libraries for building. This section will cover the installation of OpenCV in windows step by step.

1. Download the installer for OpenCV 4.2.0 (64 bit) from the following link.

https://sourceforge.net/projects/opencvlibrary/files/4.2.0/opencv-4.2.0-vc14 vc15.exe/download

Note: For 32-bit, you have to build OpenCV from the source.

2. Double click on the opency-4.2.0-yc14_yc15.exe file. The installer launch screen will appear as shown below. Select the directory in which the binaries are to be extracted. Click **Extract.**




Figure 1: Extraction location screen.

3. Once you click extract, binaries will be extracted and the window will look as shown below.




Figure 2: Extraction process screen.



Building DepthVista Application

- 1. Extract the SDK Package.
- <Extracted Directory>/Windows/Source/CPP will contain the DepthVistaCmd.sIn file.
- **3. <Extracted Directory>/Windows/Bin** will contain the SDK which includes the headers, .lib files and .dll files.
- 4. Open DepthVistaCmd Project in Visual Studio:
 - Open the new instance of visual studio.
 - Click File->Open->Project/Solution as shown below




Figure 3: Opening solution file in visual studio.

- Browse the DepthVista project and select **DepthVistaCmd.sln.**
- Choose Solution configuration (Debug / Release) and Solution Platform (Win32 or x64) (based on your requirement).

Note: Win32 and x86 are the same.




Figure 4: Choosing Solution configuration.

5. DepthVistaCmd.sln will contain two projects namely



- DepthVistaConsoleApp
- DepthVistalMU

(Note: Steps for Configuring both the projects are same. So, in this document we have demonstrated the steps for configuring DepthVistaConsoleApp project. Follow the same steps for configuring DepthVistaCmd)

- **6.** Configuring the project:
 - Right click on the project **DepthVistaConsoleApp** in the Solution Explorer and select **Properties** as shown below.




Figure 5: Opening properties page.

• Then the properties window will open as shown below. Make sure that the Configuration and Platform in the property page and in Visual Studio UI are set as same.






Figure 6: Visual Studio Property page.

 Go to C++->General->Additional Include Directories and select edit as shown below.




Figure 7: Adding Additional Include Directories.

 Enter the directory in which OpenCV include files are present and then Click OK.



Note:

- Include files will be present inside
 OpencvExtractionDirectory>\opencv\build\include.
- When OpenCV is built from source, include the following directories
 - OpenCV Build Directory>\install\include.




Figure 8: Adding Additional Include Directories.

 Go to Linker->General->Additional Library Directories and select edit as shown below.






Figure 9: Adding Additional Library Directories.

- For release build, enter the directory in which the opency world420.lib file is present. Then Click OK.
- For debug build, enter the directory in which the opencv_world420d.lib file is present. Then Click OK.

Note:

- opencv_world420.lib and opencv_world420d.lib will be present inside
 <OpenCVExtractionDirectory>\opencv\build\x64\vc15\lib.
- When OpenCV is built from source for x86 platform, **opencv_world420.lib** be present inside <OpenCV Build directory>\install\x86\vc15\lib.
 - After making all the mentioned changes click Apply button as shown to apply the made changes in the DepthVista project. Then click OK.






Figure 10: Applying changes to the DepthVista project.

- 7. Build the **DepthVistaConsoleApp** project:
 - Right click on the **DepthVistaConsoleApp** project and select Build (or rebuild) as shown below.




Figure 11: Building DepthVista project.



- Build the solution.
- Once the build is success, then you can see the message in the
 output tab of visual studio as shown below. It will also contain the
 folder in which the **DepthVistaConsoleApp.exe** is placed. It will
 usually be placed in **Release or Debug** directory from Solution
 Directory.

Figure 12: Message on successful build of DepthVista project.

 After building you can find the DepthVistaConsoleApp.exe in the respective Release and Debug folders.

Running DepthVista Application

Add runtime libraries of OpenCV (opencv_world420.dll for release build and opencv_world420d.dll for debug build) to the directory containing the DepthVistaConsoleApp.exe file.

The runtime libraries of OpenCV will be present in:

- <ExtractionDirectory>\opencv\build\x64\vc15\bin, when OpenCV is installed from installer for x64 platform.
- <OpenCV build directory>\install\x86\vc15\bin, when OpenCV is built from source.
- 1. Run the **DepthVistaConsoleApp.exe** application.
- 2. Follow the *DepthVista_Console_Application_User_Manual_Rev_1_2.pdf* provided in the package.



Support

Contact Us

If you need any support on DepthVista product, please contact us using the Live Chat option available on our website - https://www.e-consystems.com/

Creating a Ticket

If you need to create a ticket for any type of issue, please visit the ticketing page on our website - https://www.e-consystems.com/create-ticket.asp

RMA

To know about our Return Material Authorization (RMA) policy, please visit the RMA Policy page on our website - https://www.e-consystems.com/RMA-Policy.asp

General Product Warranty Terms

To know about our General Product Warranty Terms, please visit the General Warranty Terms page on our website - https://www.e-consystems.com/warranty.asp





1. Why does Windows systems headers like Windows.h, SDKDDKVer.h, gives error?

This error is due to incompatible Windows SDK Version.

- Open the property page of the project.
- Goto Configuration Proeprties->General->Windows SDK Version.
 Select any installed SDK version, and build the project again.



Revision History

Rev	Date	Description	Author
1.0	02-November-2022	Initial Draft	Camera Products